1. Home Page

1. 1 Home Page



1. 2 Home Page



1. 3 Home Page



1. 4 Home Page



1. 5 Home Page



1. 6 Home Page



2. Flight Search

2. 1 Flight Search - Outbound



2. 2 Flight Search - Outbound



2. 3 Flight Search - Inbound



2. 3 Flight Search - Inbound



3. Extra Services

3. 1 Extra Services



3. 2 Extra Services - Luggage



3. 3 Extra Services - Seats



3. 4 Extra Services - Seats



3. 5 Extra Services - Seats



4. Passanger Details

4. 1 Passanger Details



4. 2 Passanger Details - Log in



4. 3 Passanger Details



4. 4 Passanger Details



4. 5 Passanger Details - Booking Overview



5. Payment

5. 1 Payment



• On click panel verticaly animates to open state (as visible/ for interaction see prototype)
• On click on one of the payment options payment field opens on same screen and the list panel animates back to close state

5. 2 Payment



• On selection have cursor in selected field
• On type remove hint text
• Validation occurs after cursor has left the field, blue tick if correct
• If input does not match Name format > error message: Please fill in correct Full Name, no special characters allowed

• On selection have cursor in selected field
• On type remove hint text of 16 digits
• Desktop, mobile and tablet devices > no special characters are accepted
• Mobile and tablet numeric keyboard type
• On type chuck the numbers in 4 parts total 16 digits
• The field is validated after the cursor has left the field
• If the input is invalid error message: Not enough digits have been entered. Please try again
• When the user enters the 4 digits of the card, the card will be recognized.
• If card is not recognized error message: This credit card is not valid. Please enter a valid card's number.

• On selection have cursor in selected field
• On type remove hint text
• Mobile and tablet numeric keyboard type
• On type chuck the numbers in the given format with the slash (/) after the month have been entered
• The field is validated after the cursor has left the field
• If the input is invalid error message: Please enter valid date
• Option to choose dates from the calendar by clicking on arrow to prompt the drop down calendar

• On selection have cursor in selected field
• On type remove hint text
• 3 numbers only allowed in the field
• Validation occurs after cursor has left the field, blue tick if correct
• If input does not match the card details > error message: Please fill in valid Security Code

5. 3 Payment



• Pay Button activated after all the fields are filled correctly and validated
• On click payment goes through and user is taken to confirmation screen

5. 4 Booking Confirmation



• If payment succesful booking number shown and confirmation email sent
• If payment unsuccesful error message: Your payment didn't go through Please click here to try again
> after clicking user taken back to payment screen

On click back to the home screen